

CSAP

COMMON SECURITY ARCHITECTURE for PRODUCTION

VERSION 1.3

PART 1: ARCHITECTURE DESCRIPTION



Contents

1	Sec	urity	Architecture Introduction	1
	1.1	Goa	lls of the Security Architecture	2
	1.1.	1	Out of Scope	2
	1.2	Defi	inition of Security	2
	1.3	The	Role of Security in Production	3
2	Doc	umei	nt Conventions and Concepts	5
	2.1	Defi	initions	5
	2.2	Sec	urity Scalability	6
	2.3	Visu	ual Language Security Icons	6
3	Fou	ndati	onal Concepts	8
	3.1	Zero	o-Trust Architecture	8
	3.2	Extr	insic vs. Intrinsic Security	9
	3.3	Trus	st	9
	3.4	Aut	hentication vs. Authorization	10
4	Higl	h-Lev	el View of the Architecture	12
5	Cor	e Sec	urity Components	15
	5.1	Aut	hentication Service	16
	5.2	Aut	horization Service	16
	5.2.	1	Authorization Rule Examples	18
	5.2.	2	Authorization Template Example	19
	5.2.	3	Asset Protection	19
	5.2.	4	Asset Security using Access Permissions	20
	5.2.	5	Asset Security using Asset Encryption	20
	5.3	The	Authorization Rules Distribution Service	24
	5.4	Poli	cy Enforcement Points (PEPs)	24
	5.5	Mul	tiple Authorization Services and ARDSs	24
	5.6	Exce	eption Handling	25
	5.7	Dist	ributed Security	26
	5.8	Sum	nmary of Authorization and Policy	27
6	Sup	porti	ng Security Components	28

i



	6.1	Ider	tity Management	28
	6.1	.1	Access Permissions	28
	6.2	Trus	t Inference	29
	6.2	.1	Trust Learning	30
	6.2	.2	Trust Levels	30
	6.2	.3	Continuous Trust Validation	32
	6.3	Cert	ificate Service	33
	6.4	Con	tinuous Monitoring and Security Operations	33
	6.5	Thre	eat Analysis and Intelligence	34
7	Pro	ductio	on Management	35
8	Del	egatio	on	37
9	Wr	ap-up		40
	9.1		t Steps	
	9.1	.1	Interfaces	41
	9.1	.2	Policy Description	41

© 2021-2022 Motion Picture Laboratories, Inc.

This document is intended as a guide for companies developing or implementing products, solutions, or services for the future of media creation. No effort is made by Motion Picture Laboratories, Inc. to obligate any market participant to adhere to the recommendations in this document. Whether to adopt these recommendations in whole or in part is left to the discretion of individual market participants, using independent business judgment. Each MovieLabs member company shall decide independently the extent to which it will utilize, or require adherence to, these recommendations. All questions on member company adoption or implementation must be directed independently to each member company

ii



1 Security Architecture Introduction

In September of 2019, MovieLabs published *The Evolution of Media Creation – A 10-Year Vision for the Future of Media Production, Post and Creative Technologies*¹ (the 2030 Vision), which foresees that within 10 years, and likely a lot sooner, all assets of a production will be stored in the cloud, and all processing of those assets will run in the cloud.

The follow-on work, *The Evolution of Production Security – Securing the 10-Year Vision for the Future of Media Production, Post and Creative Technologies,*² asserts that as production moves to the cloud and workflows transcend organizations, protecting cloud production requires a new approach to security.

This security architecture is a framework for implementing the security model described in *The Evolution of Production Security*. The architecture is presented in six parts:³

- Part 1: Architecture Description is this document.
- Part 2: Interfaces describes the possible interfaces between the modules in a canonical form.
- Part 3: Security Levels presents a metric-based approach to scaling security.
- **Part 4: Securing Software-Defined Workflows** discusses how the security architecture can be applied to software-defined workflows that are managed using a service bus.
- **Part 5: Implementation Considerations** discusses some of the options for implementing this architecture.

Part 6: Policy Description

This document assumes that the reader has read The Evolution of Production Security.

Changes from CSAP Part 1 v1.1

- The name of the *authorization policies* has been changed to *authorization rules*.
- The functions of the policy manager moved into the authorization service, the policy service in v1.0 is now the Authorization Rules Distribution Service (ARDS). In v1.0 this was called the policy engine. This does not change the functions necessary to create an authorization rule (formerly authorization policy), but consolidation simplifies this part of the architecture.
- Security initialization has been added.

Changes from CSAP Part 1 v1.2

- The functions of the Asset Protection Service have been merged into the authorization service. There is no change in function.
- The diagrammatic representation is now three services (authorization, authentication and the ARDS) as the part of the CSAP infrastructure.

¹ https://movielabs.com/prodtech/ML-2030-Vision.pdf

² https://movielabs.com/prodtech/security/ML-Securing-the-Vision.pdf

³ Note: Part 6 has not been published as of July 2023.



• The CSAP supporting security functions Trust Inference and Continuous Trust Validation have been merged to reflect the direction of the market place.

1.1 Goals of the Security Architecture

The goal of this document is to provide a reference architecture for those implementing (e.g., software tool vendors and service providers), constructing (e.g., studios and vendors), evaluating (e.g., auditors), managing (e.g., studios), and using systems for securing the assets and processes in cloud workflows for the production of movie and TV content.

This document describes the components of the security system and the interactions between those components. It strives to balance security, availability, usability, and cost-efficiency to deliver usable security.

Every effort has been made to describe an architecture that is flexible and durable; however, we are (at the time of writing) at the beginning of the path to full implementation, and it is to be expected that the architecture will evolve as we learn more.

1.1.1 Out of Scope

CSAP is not a set of recommended practices for security or a set of security controls Every system component that is trusted must have a sufficient level of protection implemented to ensure that it is trustworthy but the standard by which that is judged is outside of the architecture. CSAP and its Policy Enforcement Points are there to ensure that only authenticated and authorized activity, for example network connections, takes place.

It is not the role of CSAP to ensure that a trusted artifact is trustworthy. How that is achieved, and the level of robustness, are matters for implementation based on, for example, organization requirements and risk analysis.

However, authorization should not extend beyond the bounds of how trustworthy something is. Furthermore, authentication does not have to be binary (authenticated or not authenticated). As we will see in section 6.2 on trust inference, CSAP has the concept of a trust score or value. Trust inference can be used to modulate whether something is trusted in a particular circumstance based on, for example, the location of a user or the device they are using.

We are at the very beginning of production in the cloud and cybersecurity is a rapidly evolving field.

1.2 Definition of Security

Our definition of security is:

- Protection from malicious and unauthorized activity, such as the exfiltration of assets.
- Protection of the integrity of data, workflows, applications, and processes.

Unauthorized activity includes, for example, activity by an unauthorized user and unauthorized activity by an authorized user. What appears to be an authorized user may be an intruder who has acquired the credentials of an authorized user.

The objects that need to be protected fall into three categories:



- 1. Assets: Data and metadata that are created, processed, and output.
- 2. Processes: Software services and user-interacting applications that process assets (including automated tasks).
- 3. Workflows: Orchestrated sets of processes acting on a set of assets.

The security threats to production are not solely the theft of assets. Simply protecting assets is not enough. Applications must be protected to ensure that their function is not subverted, or their output redirected. Only participants, whether that be a user or a vendor, authorized to work on a scene can be allowed to do so. If it is important to a production that a particular version of an application is used, that must be what happens.

The security architecture integrates with software-defined workflows, which use a highly configurable set of tools and processes to support creative tasks by connecting them through software-mediated collaboration and automation. More Information on software-defined workflows, and associated concepts such as participant and task, can be found in the MovieLabs white paper *The Evolution of Production Workflows – Empowering Creative Processes with Software-Defined Workflows.*⁴

1.3 The Role of Security in Production

The security architecture described in this document is designed for the paradigms of production in the cloud described in the 2030 Vision, which means any internet-accessible compute and storage infrastructure that uses scalable cloud technologies, regardless as to whether it is operated by a hyperscale cloud provider, in a private data center, on premises, or some combination thereof. This security architecture can be applied to any production using cloud technology.

Today, the role of production security is to address risks that are common to many businesses. The goals of security are to maintain:

- Confidentiality by preventing unauthorized disclosure, typically through the egress of data,
- Information integrity by preventing modification or destruction of data,
- Availability by preventing disruption of information or system access or use.

These risks are mitigated through security resiliency. For example:

Threat	Preparedness Strategy	
Vandalism, misconduct	Basic security hygiene	
Incursion/abuse	Critical information protection	
Presence, breach	Responsive awareness	
Disruptions, espionage	Cyber resilience	
Cyber conflict, warfare	Pervasive agility	

(Credit: Roin Nance, University of California, Berkeley)

-

⁴ https://movielabs.com/production-technology/sdw/

However, *The Evolution of Production Security* paper adds another role for production security: protecting the integrity of workflows by ensuring a workflow is conducted as intended, using:

- Approved participants whether human or machine,
- Approved/designated applications,
- Approved systems.



2 Document Conventions and Concepts

2.1 Definitions

Within this document, we use certain words to represent a broader category of similar items.

Application	Coftware that performs an operation that is part of a production worldow			
Application	Software that performs an operation that is part of a production workflow.			
	The term includes processes that operate semi-autonomously or			
	autonomously.			
Application Image	An application image running on a device where the software and the device			
	are indivisible or running in a serverless environment, that provides a set of			
	functions to clients. The application image provides one or more services or			
	microservices. We regard this as an atomic unit from the security point of			
	view.			
Artifact	Anything on the network used by the production that is not a human. That			
	includes resources, and assets, and network components that are not part of			
	the workflow.			
Attack Surface	This is the sum of the different points, attack vectors, where an attacker can			
	try to breach the security of a system.			
Device	A hardware system or a virtualized hardware system with similar			
	characteristics to a hardware system. Unless otherwise stated, no distinction is			
	made between a physical server running Linux in a data center or a virtual			
	machine running Linux on a cloud service.			
Entity	Anything that can be authenticated.			
Resource	A broad term used for anything that does work as part of a production			
	workflow that is not a human. For clarity, device, application, and application			
	image are resources.			
User	A participant (see below) that is an individual person.			
Delegation	The process of ceding some or all the management of authentication,			
	authorization, and asset protection to another organization.			

Other terms are defined in the broader MovieLabs Cloud Production work. These are:

Participant	The people, organizations, or services that do work related to a production.		
	Participants have roles associated with them that define the precise nature of		
	their work and can be related to entities such as Tasks and Assets.		
Asset ⁵	The data and metadata that are created, processed, and output by Tasks		
	during a production. The architecture does not draw any distinction in terms of		
	format or purpose. An asset is typically a file.		

The acronyms used in this document include:

⁵ This document references NIST published documents, in particular Special Publication 800-207, Zero Trust Architecture. To avoid confusion, when consulting the NIST documents be aware that the word "asset" in NIST documents is the same as the word "resource" in this document.

CSAP Part 1: Architecture Description v1.3

AES	Advanced Encryption Standard	
DRM	Digital Rights Management	
ID Identifier/Identity		
ISO International Organization for Standardization		
NIST	National Institute of Science and Technology	
SaaS	Software as a Service	
VFX	Visual effects	
VPN	Virtual Private Network	

2.2 Security Scalability

When we refer to security scalability, we are talking about scaling the level of security afforded. We refer to the ability to handle small and large deployments simply as "scalability," which is consistent with the common usage of that term.

Risk assessment is a combination of the likelihood of an event happening and the consequences of it doing so. When combined with the cost of mitigation, we get an expression of risk tolerance. Understanding risk tolerance allows decisions to be made about which risks will be mitigated and to what extent. However well the security is designed and implemented, greater security is typically more expensive. Whether formal or informal, the outcome of a risk management⁶ process is a guide as to how robust the security needs to be – the scaling of security.

This security architecture enables the security to be scaled to accommodate a production's risk tolerance and security budget.

Part 3 of the security architecture uses the construct of security levels to illustrate how security can be scaled in an ordered manner.

2.3 Visual Language Security Icons

The architecture diagrams in this document use the shapes and icons that are part of the MovieLabs Visual Language. Rather than add a key for the security icons to each diagram, we include it here.

⁶ There are many accepted methods of assessing risk, such as ISO 31000:2018, Risk Management Guidelines, https://www.iso.org/obp/ui#iso:std:iso:31000:ed-2:v1:en.

















Further information on the MovieLabs Visual Language can be found here at www.movielabs.com/production-technology/visual-language-for-media-creation/



3 Foundational Concepts

The MovieLabs 2030 Vision postulates that cloud services are common resources shared across everyone engaged in a production, be that the production company, the studio, VFX houses, finishing houses, small specialist providers and individual contributors. That presents a very different security challenge from today's use of cloud technology where the infrastructure is a hybrid cloud or data center within the control of a single entity and where few of those authorized to access the infrastructure are not employees.

In this section, we look at some important concepts that form the foundation of the security architecture.

The enterprise perimeter is no longer a location; it is a set of dynamic edge capabilities delivered when needed as a service from the cloud.

The Future of Network Security Is in the Cloud, Neil MacDonald, Lawrence Orans, Joe Skorupa, Gartner, August 30, 2019

3.1 Zero-Trust Architecture

This security architecture is a Zero-Trust Architecture⁷ (ZTA), which starts with the belief that nothing should be automatically trusted either inside or outside of any security perimeter. Instead, the rule is to verify anything and everything trying to connect before granting access.

In August 2020, NIST published SP 800-207, Zero Trust Architecture.⁸ That document presents these tenets of the zero-trust architecture:

- 1. All data sources and computing services are considered resources.
- 2. All communication is secured regardless of network location. Network location alone does not imply trust.
- 3. Access to individual enterprise resources is granted on a per-session basis. Trust in the requester is evaluated before the access is granted, and it is granted with the least privileges needed to complete the task.
- 4. Access to resources is determined by authorization policy. This includes the observable state of client identity, the application or service, and the requesting resource. It may include other behavioral and environmental attributes.
- 5. The enterprise monitors and measures the integrity and security posture of all owned and associated resources. No resource is inherently trusted. The enterprise evaluates the security posture of the resource when evaluating a request.
- 6. All resource authentication and authorization are dynamic and strictly enforced before access is allowed. This is a constant cycle of obtaining access, scanning, and assessing threats, adapting, and continually reevaluating trust in ongoing communication.

⁷ Zero Trust Networks: Building Secure Systems in Untrusted Networks, O'Reilly, Evan Gilmar, Doug Barth ISBN-13: 978-1491962190

⁸ National Institute of Standards and Technology, Zero Trust Architecture, NIST Special Publication 800-207, Abstract: https://csrc.nist.gov/publications/detail/sp/800-207/final, PDF: https://doi.org/10.6028/NIST.SP.800-207.



7. The enterprise collects as much information as possible about the current state of assets, network infrastructure, and communications and uses it to improve its security posture. This data can also be used to provide context for access requests from subjects.

Our architecture is built on these tenets.

3.2 Extrinsic vs. Intrinsic Security

The figure below shows the elements of a simple task. Today it would be carried out on a trusted infrastructure within the confines of a facility's security perimeter.




Figure 1 Extrinsic security

The security is extrinsic, meaning security is not designed into the elements, and to be secure, the work must be carried out within the confines of security imposed from outside of the workflow.

With production in the cloud, the cloud is a common set of resources across a production. It is used by the production itself, and by vendors, and by individual contributors. An all-encompassing security perimeter would be extremely complex, difficult (if not impossible) to manage, and would impinge on the creative process, making the security perimeter an undesirable option.

The solution is to create an intrinsically secure workflow like this:




Figure 2 Intrinsic security

Here, security is built into everything that makes up the workflow. It is designed to be secure on an untrusted infrastructure. To accomplish that, we use a zero-trust architecture.

3.3 Trust

To be authenticated, something must be trusted so we must first have a common understanding of what trust means.



Mayer, Davis, and Schoorman (1995)⁹ define trust as the willingness of a party to be vulnerable to the actions of another party based on the expectation that the other party will perform a particular action important to the trustor, irrespective of the ability to monitor or control that other party. This is an excellent definition for our purposes because it hints at the consequences of trusting something that is not trustworthy.

Anything that is to be trusted must prove it is the trusted entity it claims to be.

3.4 Authentication vs. Authorization

Authentication and authorization are the foundational concepts of the security architecture. They provide the answers to the questions:

- Who are you?
- Are you allowed to do this?




Figure 3 Authentication and Authorization

In this architecture, authentication and authorization are treated as separate functions. The reason for this will become clear when we address how the authorization service works.

Authentication is the process of determining that someone or something is what it purports to be. For example:

- Is this user ID being used by the person it belongs to?
- Is this system the one it appears to be to the user?
- Is this application unmodified and the correct version?

Authorization is the process of determining whether something, an action, is permitted. Once authentication has been completed, authorization addresses the questions:

- Is this user authorized to log into this system?
- Is this system authorized to run this service?
- Is this combination of user, device, and application authorized to access this asset?

_

⁹ Mayer, R.C., Davis, J.H., Schoorman, F.D., 1995. An integrative model of organizational trust. Academy of Management Review 20 (3), 709–734.

Access controls are only part of the function of the authorization service. Access controls determine whether a user is allowed to open a file, make use of a SaaS application, etc. As the name says, they are used to control access to something.

Conventional access controls are only a part of authorization: authorization asks whether the activity being undertaken is to be permitted given the full context of the activity. For example, can this user run that application on that device at this time? In that question, there are three specific elements to the context.

Authorization is a property of the activity, whereas access control is a property of an artifact such as a system on a network or a file on a file system.

Finally, the distinction between authentication and authorization should not be taken to mean that the architecture cannot be built using an identity and access management (IAM) system. Implementation is outside the scope of this document.



4 High-Level View of the Architecture

CSAP is a collaboration-oriented zero-trust security architecture. It is concerned with securing and protecting the integrity of assets, processes, and workflows in the collaborative environment of media production. CSAP assumes that artifacts that are trusted are trusted because they are secured and it is not concerned with protecting the underlying infrastructure, and as discussed in Section 3.2, it is designed to protect production on an infrastructure that is not trusted.¹⁰

Trusted artifacts must be secured to the level required for them to be trusted, and that level might be set as an implementation requirement, or a security requirement set by a vendor's clients. The role of CSAP is to manage access to and by those artifacts.

This architecture creates workflows with intrinsic security.

The security system authorizes activity at the direction of production management, a term used here to describe the point(s) of control of production activity.

The CSAP architecture is designed around a control plane and a data plane. The security control plane is divided into two sets of components: core security components and supporting security components. It is driven by production management operates in the security context of organization security policies that include the current security stance. It provides security functions such as security decision making, messages that enable activity, 11 and the services required to make that operate.




Figure 4 CSAP high-level architecture

¹⁰ This does not mean that perimeter security cannot be used. An implementation could make use of a security perimeter, a software-defined perimeter (SDP), or microsegmentation.

¹¹ CSAP is deny-by-default and authorization rules only authorize activity, they do not need to deny it.



The security data plane is where the security policies created by the core components are acted upon. It is embedded in the operation of the production cloud. The security data plane includes the workflow management discussed in detail in "Part 4: Security and the Software-Defined Workflow."

The distinction between core components and supporting components is based on the need for domain knowledge of the application.

The core components need domain knowledge of the application; they act in a way that is specific to securing production.

- Authentication Service. Identity is at the core of the architecture; the authentication service authenticates users, devices, and applications. 12
- Authorization Service. Driven by workflow management, this service enables access to resources and assets according to the production's chosen security profile by creating authorization rules. This service also maintains a record of the authorized access to protected assets.
- Authorization Rules Distribution Service (ARDS). This service distributes authorization rules to the policy enforcement points.

Closely coupled to the core security components are:

• Policy Enforcement Points (PEP). PEPs interact with infrastructure, services, etc. to enable authorized, and only authorized, activity to take place.

The supporting components do not require application domain knowledge to provide the services used by the core components. It is expected that the secondary components can be implemented using off-the-shelf security components, including those provided by the hyperscale cloud providers and by vendors offering security-as-a-service.

- Identity Management
- Trust Inference
- Continuous Trust Validation
- Certificate Service
- Continuous Monitoring and Security Operations
- Threat Analysis and Intelligence

The two primary components of production management that are integrated with the security architecture are:

- Workflow Management. This initiates tasks, specifying what is to be done, where it is to be done, and who or what is to do it. In its simplest form, it is a work scheduling system generating work orders. It could be an orchestration system.
- Asset Management. This identifies the assets required for a task and the means to locate the
 asset.

-

¹² The Authentication Service is not necessarily a <u>server</u> engaged in every authentication verification. For example, authentication can be carried out in the identity management in the supporting security components.

The architecture can be implemented as a distributed system with multiple instantiations of the core security component services. There is no inherent design decision that prevents such an implementation, although additional design work may be needed to coordinate a distributed system. It is expected that there will be multiple workflow management and asset management systems.

The next sections look at these components in more detail, starting with the core security components and then looking at the supporting security components.



5 Core Security Components

Security is controlled by the four core security components.

These are:

- The authentication service.
- The authorization service.
- The authorization rules distribution service.




Figure 5 Detail of Core Components

Production activities are secured by the authentication and authorization services acting in concert to enable approved activity. If we go back to our simplistic view of a secure task, and remembering that this is a conceptual example, the authentication and authorization services act as follows:




Figure 6 Authentication and authorization enable secure activity



When generalized, the "user" in Figure 6 would be a "participant" as defined in the MovieLabs Ontology. 13

5.1 Authentication Service

At the very heart of the architecture, and any ZTA, is identity. Nothing is permitted to happen without every involved entity being authenticated.

Every participant (e.g., users, application services, etc.), application, and device has an identity, and the identity has attributes assigned to that account or resource. Attributes can include device characteristics such as software versions installed, network location, time/date of request, previously observed behavior, and installed credentials; it can include application characteristics such as version and signature. Once authenticated, these characteristics are trusted.

The authentication service is a policy-driven service responsible for authenticating and maintaining the authentication of the identities of participants, devices, and applications. The authentication service policies determine how it authenticates entities and how that authentication is managed over time.

It uses four of the supporting security components.

- Identity management and trust inference are used when first establishing or re-establishing trust. The balance between using only identity management, which implies a full credential check, and using the trust score from the trust inference service is a policy set by security administrators. The goal is to reduce the overhead of authenticating entities, particularly users.
- Certificate management provides the certificates and other cryptographic elements used for the creation of tokens and identification of entities, particularly ones that are not users.
- Continuous trust validation supplies the authentication service with alerts when the context of the original authentication changes and lowers the trust score.

5.2 Authorization Service

The authorization service is a policy-based service that authorizes an activity to take place. Specifically, it creates authorization rules that authorize the elements of the workflow to participate and access the required assets. The creation of an authorization rule starts when the workflow management system sends an authorization policy request to the authorization service. If it does this ahead of the time that the authorization rule is needed, the process of authorization does not introduce any latency to the workflow. Authorization policy requests can be sent when the workflow is set up or initialized as well as when the workflow is executing, and they can live for as long as is needed.

A policy is a statement defining what is authorized or what must be denied, a rule describes a policy in a way specific to the policy enforcement point it is directed to. A policy template is the means to convert from a policy to a rule.

Authorization rules are passed to the authorization rule distribution service (ARDS), see section 5.3, to be distributed to the policy enforcement points.

¹³ https://movielabs.com/production-technology/sdw/




Figure 7 Policy creation flow

All authorization rules start with an authorization policy template which is created when security for the workflow is initialized (set up) or if something changes (such as the interface to a resource). The template reflects the security requirements of the production derived from risk management, including risk tolerance and cost along with other parameters specific to the workflow and stage of production. There is no requirement for authorization policy templates to be universal and they may be specific to the infrastructure that they apply to even if the same activity is being authorized on each.

Global security policies are created when there are overarching security or business limitations on what can be done. They might come from outside of the production such as the studio, from production management, or are created because of the current security stance. We refer to the sources collectively as Global Security Management.

They describe what is not allowed, such as infrastructure, users, applications, etc. For example, a security breach in part of the infrastructure results in the creation of a global security policy that blocks use of that part of the infrastructure, and that global security policy is revoked when the breach is mitigated.

Handling of global security policies in the authorization service is unique in CSAP in that it is approve-by-default meaning that unless one of these policies denies something, the authorization rule is created. Otherwise, throughout CSAP, the principle is deny-by-default. If an authorization policy request has a component that is disallowed by global security polices, workflow management should be notified but it is not the role of the authorization service to arbitrate.

Authorization rules are:

Constructed from access permissions based on attributes assigned to a user or device, to the
asset, etc., and from environmental rules based on attributes such as network location, time,
etc. They can be applied to resources and assets using common access control methods such as
ACLs. These policies implement the principle of least privilege spatially.

- Constructed in response to instantaneous operational requirements, e.g., work being scheduled
 in a workflow. Authorization rules constructed in this way may last no longer than the duration
 of an activity and cover no more than the resources involved in a workflow. These authorization
 rules implement the principle of least privilege spatially and temporally.
- Consistent with global security policies.

A wide range of granularities is possible for authorization rules. For example, authorization to provide access to assets might range from authorization to access all a production's assets to authorization to access just the assets required for the immediate task for the duration of that task.

5.2.1 Authorization Rule Examples

A production management system at a VFX company assigns a VFX artist to work on a particular shot to be carried out over the next four days, and the authorization service is notified of the assignment. Depending on the need, policies can be constructed that:

- Permit the user to conduct the activity because the user is a member of a group permitted to conduct the activity.
- Permit the user to conduct the activity only during the time that the user is scheduled to do it.

Since a ZTA is built on the principle that only authorized activity is permitted, there is no need for the notion of "forbid" in policies since CSAP is deny by default.

Authorization for the participant to conduct the activity could be a result of the application of both of those policies.

• The participant is a member of a group permitted to conduct the activity AND the user has been assigned the activity.

In this case, authorization will be granted to the user who has been scheduled by the production management system (expressed in the authorization policy), provided that the user is permitted to conduct that activity in general.

An example of a global policy would be a policy that prohibited the use of a particular vendor, and the authorization service would reject any request to generate an authorization rule that involved that vendor.

An example of a change in the security stance would be the discovery of a security vulnerability in a version of an application meaning that authorization service could not generate a policy that authorized work using that application.

A different example of a change in the current security situation would be the determination that a user's account credentials had been compromised. Such as case is not handled by the authorization service but by the authentication service illustrating the "division of labor." An authorization policy authorizes <u>authenticated</u> participants to be part of an activity. If the security of the participant's authentication has been compromised, the need is to ensure that the participant is not authenticated until the issue is resolved.



5.2.2 Authorization Template Example

In our example, a production is using AWS, Azure, and Google Cloud to perform the same function. However, since security management differs between these vendors, a different policy template would be required for each as illustrated in the following diagram which builds on Figure 7.




Figure 8 Resource specific authorization rules

The authorization service is applying the same authorization policy request to the three resource specific templates to generate resource specific authorization rules.

5.2.3 Asset Protection

Traditionally the way assets are protected is by controlling access to the files and storing them on encrypted media. *The Evolution of Production Security* paper points out that the security goal is to protect the asset and not the storage container in which the asset is stored.

This architecture can protect assets individually. Controlling who can access an asset is a better security proposition than controlling who can access the storage. Controlling access at the asset level means least privilege — users are only granted access to the assets they need. Controlling access at the storage level means that some users are granted access to the assets they need and other assets in the storage container which they do not need. This is true regardless of the type of storage and network, although the implementation may be dependent on the type.

Two primary methods of protecting assets are:

- The use of the access permissions supported by the infrastructure (file system, cloud provider, etc.)
- Encrypting the assets with individual keys.

These are not mutually exclusive, and assets can be protected in different ways along their journey.

The authorization service is responsible for tracking how assets are protected.



5.2.4 Asset Security using Access Permissions

Controlling access to resources using access permissions is a well understood discipline, and there are many ways to implement them.

One approach is the use of access-control lists (ACL). An ACL is a data structure containing entries that specify individual and groups rights to specific artifacts. It is an artifact-based access control.

The simplest example is the access control attributes of a Unix file where rights to read, write and execute can be assigned to a single user, a single group of users, or everyone. More generally, this is a mechanism that implements access control for a system resource by enumerating the identities of the system entities that are permitted to access the resources.¹⁴

Another approach is using role-based access control (RBAC). Role permissions may be inherited through a role hierarchy and typically reflect the permissions needed to perform defined functions within an organization. A given role may apply to a single individual or to several individuals. FBAC is regarded as "higher" level method since it ties permissions to specific operations with significance to the organization.

A third approach is attribute-based access control (ABAC), an access control paradigm whereby access rights are granted to users through the use of policies that combine attributes together. The policies can use any type of attributes (user attributes, resource attributes, environment attribute etc.).¹⁶

If access controls are used to protect individual assets, they will be implemented in the as part of an access control system that is part of the infrastructure, whether that be the file system access controls or full-functioned access management from a cloud provider.

The requirement is that only access authorized by the authorization service is possible. Conversely, there should not be any roles such as administrators or superusers that can circumvent the access controls or change permissions. That requires informed management of administrator accounts.

5.2.5 Asset Security using Asset Encryption

When asset encryption is used, granularity can be adjusted using strategies such as an individual encryption key for each asset or an encryption key for a group of assets. (In this latter case, whether each asset is encrypted separately using the same key, or the assets are encrypted as one group, is an implementation choice that may not materially affect security.)

The process of granting access starts with the identification of an asset that is needed. That happens when a user or process attempts to access the asset (on demand) or when an activity is scheduled that uses that asset (pre-loading).

The term "encryption at rest" is often used to refer to storage encryption as distinct from encryption during transfers, often referred to as "encryption in transit." Encryption at rest is imprecise. For the

¹⁴ NIST SP 800-82 Rev. 2

¹⁵ NIST SP 800-53 Rev. 4

¹⁶ NIST SP 800-192



purposes of CSAP, we categorize encryption of stored assets we define two classes, which are not mutually exclusive:

- **Implicit encryption**. We define implicit encryption to mean that whatever is holding the asset (a storage "container," ¹⁷ such as a disk, or a filesystem volume) is encrypted. Typically, the encryption is a property of the infrastructure; the container is encrypted as a property of the storage mechanism.
- **Explicit encryption.** We define explicit encryption to mean assets are encrypted individually or as a group such that the encryption is independent of how the assets are held. We refer to this as "asset encryption." It is also referred to as "file encryption."

Access to assets protected by implicit encryption is controlled primarily by access controls. It protects only from an attacker who does not have access privileges (or cannot circumvent them) but has direct access the storage medium (e.g., an attacker who steals a laptop and removes the hard drive). However, access to assets protected by explicit encryption is controlled by selective distribution of encryption keys. Any form of explicit asset encryption requires a key distribution service. Where implicit encryption is used in a workflow today, assets are encrypted at certain points in their journey: they are stored in encrypted containers (e.g., encryption at rest or hard drive encryption) and transferred by encrypted file transfer protocols. As the asset moves around, it goes through a series of encryption/decryption cycles as shown in the following diagram.




Figure 9 Encryption/decryption cycles of point encryption

However, explicit asset encryption supports end-to-end encryption. An asset is encrypted when it is created and is only decrypted on use. If we apply asset encryption in the diagram above, it looks like this:



Figure 10 End-to-end asset encryption

_

¹⁷ Including object storage, file storage, block storage, volume storage, hard drives...



Two things are obvious. The latter process is simpler, there are no special requirements on the storage or file transfer and there are fewer attack surfaces – each point where the data is unencrypted has an attack surface.

If access to assets is controlled by encrypting the assets, there is there is less reason to protect them further unless you believe the encryption system will be broken during the value lifespan of the assets 18 or that the encryption keys will be vulnerable to unauthorized access. As a small amount of data, an encryption key is easier to move around and easier to secure than any asset file. If the keys can be sufficiently well protected, the encrypted files can be visible to all and can be managed (for example, copied) by anyone, but only those authorized can open the encrypted file to get access to the clear contents. 19 And in almost any scenario, a combination of some access controls on the encrypted assets and tight access controls on the encryption keys can improve the protection of assets over that of workflows without end-to-end asset encryption.

The key protecting the content should be accessible only to dedicated software-based or hardware-based trusted components.²⁰ For example:

- The trusted component could be in the application. If so, it might be a small piece of secure code used at the point that assets are read and written.
- The trusted component could sit between the application and its storage. If so, it might be a wrapper through which assets are read and written, or it might be a hardware component in the file access used by the virtual machine on which the application is running.

This form of asset encryption is routinely used in the distribution of content to consumers, and at the content encryption level there is a similarity between how DRM content encryption works and what is needed for asset encryption. (DRMs also convey rights information, but that function is not relevant to this discussion.)

_

¹⁸ Scott Fluhrer, "Reassessing Grover's Algorithm," IACR Cryptology ePrint, August 27, 2017, https://eprint.iacr.org/2017/811, posits that quantum computing will not break AES.

¹⁹ Of course, the assumption is that the encryption algorithm used is AES-128, AES-192, or AES-256 in the appropriate mode of operation. Currently, there are no known attacks on the AES algorithm where someone without knowledge of the key can read data encrypted with AES. The threat surface is insecure implementation and bad key management. See https://en.wikipedia.org/wiki/Advanced Encryption Standard#Known attacks.

²⁰ Further information on NIST projects on roots of trust can be found using this link https://csrc.nist.gov/Topics/Security-and-Privacy/risk-management/roots-of-trust.




Figure 11 Asset encryption in streaming service and in production

We are not advocating that the solution is to use an actual DRM, but some useful parallels can be drawn.

Asset encryption can be done without solution lockin. If a common encryption algorithm operating in the same mode is used, for example AES-128 CTR mode, multiple solutions for content encryption can be used in parallel.

Consumer streaming services usually use more than one DRM because one DRM might be the only viable choice on one client platform but might not be available on another platform. For this reason, the majority of streaming services use more than one DRM. The same encrypted content is delivered to all players, but the key is delivered by the DRM that is supported by the target player. This is shown in Figure 12.

If asset encryption is used, it is not in the interests of the ecosystem to have a single technology provider, to require everyone working on a production to use the same technology, or to use only a technology that can be implemented on every platform.




Figure 12 Asset encryption using multiple key distribution technologies



5.3 The Authorization Rules Distribution Service

The ARDS delivers authorization rules created by the authorization service to the policy enforcement points. Its role is to direct the policy enforcement points (PEPs) in real-time and in accordance with the authorization rules passed to it. Ideally, authorization rules can be cached at the PEP, and cached ahead of work being done.

While it is advantageous from the point of view of minimum impact on workflows to generate authorization rules ahead of the initiation of an activity, consideration should be given as to how far ahead of time the ARDS loads authorization rules into the PEP. Ideally, that would be just in time.

5.4 Policy Enforcement Points (PEPs)

Up until now, we have been describing the security system control plane. Now we are at the security system data plane.

The PEPs are embedded in the network, the devices, the applications, the storage system, the workflow management service bus, and so on. They enable authorized, and only authorized, activity to take place.

PEPs will vary according to the artifact they are protecting.

The description of the CSAP architecture uses the term *policy enforcement point* in a broader sense than is used NIST Special Publication 800-207.




Figure 13 NIST SP 800-207 Zero Trust Architecture

CSAP PEPs may include functions that are part of the SP 800-207 policy decision point. Furthermore, enforcement of CSAP policies may be done in functions provided by the infrastructure (for example, attribute-based access controls) and the CSAP PEP is setting the parameters that authorize the appropriate access.

5.5 Multiple Authorization Services and ARDSs

The architecture supports:

An authorization service using more than one ARDS (authorization rules distribution service)



• An ARDS receiving authorization rules from more than one authorization service

The architecture is constrained such that:

A PEP can receive authorization rules from only one ARDS




Figure 14 Example of multiple authorization services and multiple ARDS

5.6 Exception Handling

There will be times when a policy enforcement point blocks an action, and it will be because the action is either:

- 1. An attempt to do something unauthorized, or
- 2. An attempt to do something that should have been authorized but has not been.

However, the PEP does not know which it is. All it knows is that something was attempted that is not allowed. The PEP cannot be expected to determine that something was almost allowed, for example all but one condition in an authorization rule was met, although that could be part of the implementation.

CSAP does not require either PEPs or ARDS to handle exceptions. The limits of CSAP's requirements are that no activity should be allowed unless it has been authorized.

The PEP could be implemented so that it sends an exception back to the ARDS. However, a flood of exception messages could result in denial of service.

If an exception is sent back to ARDS, it can do one of two things:

1. Send a new policy to the PEP, which will happen when the ARDS has a policy that allows the action, but the policy has not yet been sent to the PEP, or

2. Pass the exception back to the authorization service if, and only if, it can determine the relevant authorization service

If the authorization service receives the exception there is nothing it can do with it except pass it to workflow management and, in a real-world production with multiple workflow managers, the authorization service may have to notify all of them.

However, unless a new policy is sent to the PEP and the action allowed, the attempted action will fail and whatever initiated the action will become aware of the problem.

It is also worth noting that we have described are exceptions generated by a PEP, but the PEP can only generate an exception if it is responsible for directly allowing or denying an activity. A PEP may be authorizing activity indirectly. For example, if asset protection is being achieved by storage access control lists (ACLs), then the PEP might be authorizing access to assets by setting the ACLs. When an attempt is made to access an asset, the PEP is no longer "in the loop" and a rejected access request would be sent to back to the application and to any logging system but not the PEP.

As with systems today, workflow management and asset management are assumed to be trusted – a subverted workflow management system can initiate activity that should not be permitted. The core components can validate the source of information sent from the workflow management and asset management systems, but unless the requests violate global policies, the core components cannot determine whether an activity should be authorized or should not. This can happen with existing security systems, possibly with fewer safeguards.

CSAP does not place any requirements on the ARDS, PEPs or the authorization service to handle exceptions since they will be implementation specific.

5.7 Distributed Security

This architecture supports the distribution of its components. There is, rightly, no single source of failure built into the architecture (although there may be in a particular implementation). There are many ways that the security can be distributed. Here are some examples:

- 1. A production has more than one workflow manager and an authorization service is associated with each workflow manager.
- 2. Authorization is delegated; for example, authorization for some part of a production is delegated to a vendor responsible for that work.
- 3. Separate security systems are deployed for each department involved in a production and authorization is hierarchical: the top tier authorizes the department to conduct a workflow, a second tier authorizes each task carried out by the department.
- 4. Policy services are specific to one class of authorization rule. For example, one policy service handles policies to do with processing and the other handles policies to do with asset access.
- 5. Services are replicated as a means of adding resilience, scaling capacity, and reducing latency by putting services close to where tasks are conducted.

There is nothing in the architecture that precludes any of these examples, or indeed distribution in general, but of course additional design work will be needed to define how this will work.



5.8 Summary of Authorization and Policy

The authorization service creates authorization rules by applying security policy templates, created when the security is initialized, to authorization policy requests from workflow management. These authorization rules will comply with global security policies created, for example, in the context of the security data from the continuous monitoring and security operations service and the threat analysis and intelligence service. The result is passed to the ARDS which controls the policy enforcement points.



6 Supporting Security Components

Supporting security components are services used by the core security components to fulfill their roles.




Figure 15 Detailed view of supporting components

This section describes the functionality of the supporting security components and the interaction with core security components.

The architecture defines the interfaces between the individual core component services using the six function components in Figure 15, but it does not define anything about the internal architecture or implementation of the supporting security components.

6.1 Identity Management

Identity is at the core of any zero-trust architecture and of this security architecture. A robust way of verifying that a user, device, or application is what they claim to be is essential.

The identity management service would ideally be a single sign-on (SSO) system; however, it is not a requirement as long as the authentication service knows where to verify an identity.

The identity management service may be a federation of identity management systems, which is a group of mutually trusted identity management systems.²¹

Principle 6 in the 2030 Vision Paper states "Every individual on a project is identified and verified and their access permissions efficiently and consistently managed." A MovieLabs work item arising out of this is work on a Production User ID (PUID), one function of which is to provide an identity management service for users with a PUID. That service would be part of an SSO federation.

6.1.1 Access Permissions

IAM systems provide both identity management and management of user access privileges. Here we distinguish between the two functions. The identity management part of IAM is used by the

²¹ https://en.wikipedia.org/wiki/Federated_identity

authentication service, and the access management part can be used by the authorization service. Figure 16 illustrates this point.




Figure 16 Relationship between an IAM and authentication and authorization

6.2 Trust Inference

Trust inference is the use of intelligence on user and device behavior to infer the level of trust that can be assigned at the time of an authentication request. It is also referred to as risk-based authentication.

Risk-based authentication is a dynamic component of authentication systems that considers parameters other than the credentials presented to determine how to perform authentication.

For example, if a website frequently presents a captcha challenge when you attempt to log in, that may be a result of a trust assessment that has detected something out of the ordinary, such as an IP address with a different locale from your usual log in location.

The level of trust that can be inferred may be used to increase or decrease the complexity of the authentication mechanism. If the trust inference yields a high score, user authentication may happen with a simpler PIN. For example, the PIN on a Windows 10 workstation is not as complex as a password because trust is inferred by the user typing on a physical keyboard attached to the computer.

When trust inference yields a low score, additional measures could be required, up to and including identifying the authentication request as an attempted intrusion and denying the request regardless of credentials presented.

This has two benefits for the production. In addition to increasing the security of the authentication, it lightens the touch of the user authentication process, often a point of friction for the user.

Denying an authentication request based on trust inference need not affect legitimate activity. By differentiating between a possible attack and a legitimate log in attempt, user activity that scores well on trust inference is unimpeded, whereas activity that scores low in trust inference can be blocked.

Denying an authentication attempt because it has a low trust score is not the same as locking the user account after a certain number of failed password attempts. That method of blocking an attempted intrusion also blocks legitimate access. Trust inference could block login attempts with a particular set of parameters (e.g., geographic location), while not interfering with other login attempts for the same account with a different set of normally present parameters.

Of course, levels are set as a matter of policy by the organization and do not have to be uniform for all users and devices.

A common method of trust inference is contextual or risk-based authentication management. An example is:



Location Context

- New city, state, or country
- New geo-location
- Impossible travel



- Atypical device type
- New device
- Managed device



Network Context

- New IP
- Specific IP zones
- Network anonymizers
- ISP ASN

Figure 17 Contextual access management (source: Okta)

Trust inference can also be used to deal with devices that are subverted, have known vulnerabilities, or are not managed by the production. These devices may be treated differently (including denial of all connections) than devices owned or registered by the production that are deemed in a secure state.

Both trust inference and continuous trust validation use behavioral attributes, including automated subject analytics, device analytics, and measured deviations from observed usage patterns.

By using trust inference and continuous trust validation (Section 6.2.3), the authentication service is able to reduce the burden on users to present credentials when they log into a new system, while also increasing security by requiring re-authentication or denying access when artifacts engage in unexpected behavior.

6.2.1 Trust Learning

Production is a fluid environment. Processes change during a production and from one production to another. Production is carried out by a substantial number of individuals contracting directly with the production or employed by any number of other organizations such as the studio, post houses and VFX companies.

The operation of trust inference and the associated continuous trust validation, described in Section 6.2.3, uses knowledge of the expected behavior that can be learned from the activities over a period of time, correlating activity with authorized activity, and so on.

6.2.2 Trust Levels

Trust inference considers multiple factors, so the outcome is not necessarily yes or no. If, for example, 4 out of 5 factors were satisfied the trust score might be 80%. To turn that into a yes or no would require a trust threshold where the trust score is assessed to be either above or below that threshold.

However, a more sophisticated implementation might use the trust score to determine what can be authorized and what cannot. That trust score could be part of the conditions to be met in an

authorization rule. To be authorized for an activity, entities must be authenticated with a trust score above a threshold value. Low risk activities might have a lower threshold.

BeyondCorp incorporates this concept.

One of the fundamental components of BeyondCorp is the trust inferer.

Osborn, McWilliams, Beyer and Saltonstall ²² describe the BeyondCorp *Trust Inferer* which is a system that continuously analyzes and annotates device state. The system sets the maximum trust tier accessible by the device and assigns the VLAN to be used by the device on the corporate network. The trust tier is like CSAP's trust score.

BeyondCorp's trust tiers are assigned to each device by the Trust Inferer.

"As a device is allowed to access more sensitive data, we require more frequent tests of user presence on the device, so the more we trust a given device, the shorter-lived its credentials. Therefore, limiting a device's trust tier to the minimum access requirement it needs means that its user is minimally interrupted. We may require installation of the latest operating system update within a few business days to retain a high trust tier, whereas devices on lower trust tiers may have slightly more relaxed timelines."

Trust inference for a device comes from two sets of data.

- Observed data generated from data collected such as the last time a security scan was performed on a device, the OS version and patch level, any installed software
- Prescribed data which is manually assigned and might include the assigned owner of the device, users and groups allowed to access the device, DNS and DHCP assignments and explicit access to particular VLANs

Data is analyzed from a variety of disparate sources to identify where data conflicts. There is no single or small number of systems that are regarded as the source of truth.

_

²² BeyondCorp: Design to Deployment at Google, Barclay Osborn, Justin McWilliams, Betsy Beyer Max Saltonstall, ;login:, vol. 41 (2016), pp. 28-34, https://www.usenix.org/system/files/login/articles/login_spring16 06 osborn.pdf

CSAP Part 1: Architecture Description v1.3




Figure 18 The BeyondCorp data processing pipeline (Source: Google)

Here the trust evaluation overrides the access control engine, and this is one way to implement not only initial trust inference but also CSAP's continuous trust validation.

6.2.3 Continuous Trust Validation


In the previous section we described trust inference, i.e., the use of activity intelligence in the decision to establish trust.

Continuous trust evaluation is the process of determining if an established trust relationship should still be trusted.

Question	Mechanism	
Should I trust this entity?	Identity management and trust inference	
Should I still trust this entity?	Continuous trust evaluation	

The same, or similar, parameters used in trust inference are collected from real-time activity intelligence, including data acquired by network and system logging. Analysis of that activity determines whether a trusted entity should still be trusted.

A simple example is a situation where trust is established for a user connecting from one IP address and in mid-session the IP address changes to a different one in a different region. A circumstance like this might happen when an attacker is using a mechanism to disguise location such as Tor (anonymity





network²³) or a VPN. The change in the IP address triggers an "impossible travel" rule²⁴ and the trust is revoked.

When continual trust evaluation detects a potential issue, it does not always have to result in the immediate termination of user activity. It may trigger reauthentication or increased surveillance.

When the trust score created by trust inference is at the lower end of the acceptable range, it may be that the continuous trust validation uses tighter constraints so that even a slight negative change in the trust assessment alerts the authentication service to take action, such as re-establishing trust through re-authentication.

6.3 Certificate Service

The certificate service is the certificate authority responsible for generating and tracking certificates issued to users, systems/devices, applications, and the asset protection service, as well as managing and distributing Certificate Revocation Lists (CRL).

The certificates are used for cryptographic purposes throughout the system.

All certificates are revocable and system components using the certificates should check current validity and not rely solely on expiration times.

It is an implementation decision as to whether the certificate service is a public or private certificate authority.

6.4 Continuous Monitoring and Security Operations

Continuous monitoring and security operations (CMSO) is a set of functions conducting real-time analysis of multiple data sources to provide situational awareness to other security components and to the information security operations center (ISOC).

The functions that fall under the header of continuous monitoring and security operations include functions variously known as:

- Network security monitoring
- Continuous security monitoring
- Continuous diagnostics and mitigation

Together these functions:

- Monitor system and network activity
 - The collection and analysis of data about network traffic, access requests, processes, locations, and so on.
- Monitor user actions

²³ https://en.wikipedia.org/wiki/Tor (anonymity network)

²⁴ For an explanation of impossible travel and how the Microsoft Cloud App Security addresses it, see https://www.daymarksi.com/information-technology-navigator-blog/understanding-office-365-impossible-travel.

- The collection and analysis of data about user actions, including authorized activity, attempts at unauthorized activity, user location, and so on.
- Monitor assets
 - The collection and analysis of data about access to assets, movement of assets, network traffic associated with access to assets, location of assets

These functions provide the security architecture with notification of security events, including attempted intrusions and devices falling out of compliance with security requirements.

The data collected may also be used for provisioning cloud resources and networks, as well as generating alerts for system performance problems.

6.5 Threat Analysis and Intelligence

The functions under the heading of threat analysis and intelligence provide analysis of the threat environment based on the collection of data from within the security system and outside of it. The emphasis here is on the depth of analysis rather than real-time sensors.

- Security information and event management (SEIM) collects security-related data for later analysis. This data is used to refine underlying policies and warn of possible attacks.
- Threat intelligence collects information from internal and external sources that helps in the management of authentication and authorization rules.
- Activity logs are collected from devices, network components and security enforcement points.



7 Production Management

The purpose of the security system is to enable secure production. Consequently, the core security components are directed by production management to authorize work.




Figure 19 Interaction with production management

The workflow management system notifies the authentication service of the participants, devices, application services and applications that are part of the workflow so that the authentication service can ensure proper authentication. The notification might be applicable to a group of participants or devices, or a range of versions of an application.

The workflow management system sends a complete description of the workflow (or a part of it) to the authorization service. That description includes:

- A list of the participants, devices, application services and applications
- A list of tasks along with parameters such as duration of the task

The asset management service sends a list in the form of asset identifiers and locators of the assets that are required for the workflow. Note that in CSAP Part 4: Securing Software-Defined Workflows we will see that this can be complicated if indirection is used to locate assets.

A timeline of the interaction between production management, the core security components, and the supporting security components looks something like this:

CSAP Part 1: Architecture Description v1.3




Figure 20 Flow of workflow authorization

The exact flow of workflow authorization depends on how workflow is managed. For example, if workflow is managed by a traditional scheduling system that creates work orders, operation is different than if the workflow is managed by an orchestration system.



8 Delegation

As stated earlier, the cloud is a common resource for everyone working on a production where data is stored, and applications and services are run. That means that multiple organizations and individuals will be using the resources, and CSAP is a response to the difficulty in managing security in that context.

In this section, we are addressing delegation which we defined earlier as the process of ceding some or all the management of authentication, authorization, and asset protection to another organization. Traditional workflows, where data is moved to a vendor, mean that a vendor has complete control of all three for the data that is sent to them.

The MovieLabs ontology defines Participants as the entities (people, organizations, or services) that are responsible for the production of a Creative Work. People are the individuals that are contracted or employed to perform given tasks on a production. Organizations are groups of people or legal entities with a particular purpose relative to the production.

Single sign-on is the ability to sign-in or log into the platform once and be able to use different applications in the platform or suite without having to enter in your credentials several different times which is certainly a benefit to the user.

Same sign-on requires you to log into each application but using the same userID and password which helps end-users by reducing the number of userID and passwords to remember.

Core BTS Blog²⁵

Participant authentication is foundational to CSAP. Even if all participants can be treated as individuals, we cannot constrain the operation of CSAP to a single identity management system even if it is a single sign-on (SSO) system, which is a form of federated identity management, or same sign-on also known as Directory Server Authentication.

Let's take an example where the studio (the content's owner) provides cloud infrastructure for the production to use. All the production's assets will be stored in that cloud and the production's vendors are using it – either working on the assets directly or copying them to the vendor's infrastructure, whether another cloud instance or local storage.

Let us use an example where the production is making use of the services of four vendors:

- ACME Post, a large post-production services vendor that has served the studio for a long time
- Globex VFX, a medium-sized VFX vendor working with a studio production for the first time
- Cottage Sound, a 3-person sound mixing company
- Hamilton, a freelance VFX artist specializing in rapidly fixing problematic footage

²⁵ https://corebts.com/blog/office-365-single-sign-on-vs-same-sign-on/




Figure 21 Example relationships between studio, production, and vendors

The studio and the production may have different levels of trust in the security capabilities each of these vendors. For example, Acme Post has an experienced information security (InfoSec) team whereas Cottage Sound outsources system management to a one-person IT company with unknown InfoSec skills, and Hamilton manages their own system.

Delegating control of security starts with treating an organization as a single participant. Authorization rules authorize the organization to conduct an activity with sufficient granularity, for example authentication of individuals within the organization, are the responsibility of the organization meaning authentication is delegated to the organization.

In our example, delegation to each vendor might look like this:

Organization	Authentication	Authorization	Asset Protection	Explanation
Acme Post	Delegated	Delegated	Delegated	ACME is responsible for all aspects of security
Globex VFX	Delegated	Delegated	Not Delegated	Production maintains control of asset protection
Cottage Sound	Delegated	Not Delegated	Not Delegated	Production maintains control of authorization of activity
Hamilton	Not Delegated	Not Delegated	Not Delegated	Hamilton is treated in the same way as any member of the organization

In the case of Acme Post, Globex VFX and Cottage Sound, authentication is delegated for two reasons: it is more resilient since it does not depend on full-time low latency access to the production's authentication service, and it allows Acme Post, Globex VFX and Cottage Sound to keep confidential aspects of their business such as the number of people working on a project. Thus, the production authorization rule authorizes an activity with, for example, Acme Post as the participant and then Acme Post creates a corresponding authorization rule where the participant is an individual or a group of individuals. And so on for authorization and asset protection.

InfoSec capability isn't the only reason to do less than 100% delegation. The production may want to know when someone at Globex VFX accesses an asset and maintaining control of assets is one way to determine that.

Delegating asset protection in the case where the vendor works directly on assets stored in the cloud may require some sophistication when access control lists are used. The production would likely give the vendor access privileges in the same way as any other participant but doing so requires that the vendor has a way of adding granularity of access privileges, probably in a secondary system. If asset encryption is used it is conceptually simpler – keys are made available to the vendor as with any participant and the vendor has a key management system.

If a production's authorization rule requires that a vendor's individual participant or group of participants is identified, it is possible (security considerations aside) for the vendor to use anonymized identifiers. Of course, good security practices would dictate that records are kept of the mapping from participant to anonymized identifier.

In conclusion, CSAP does not require monolithic control of the security. Delegation allows the option for organizations working on a production to control their security. It is also not a prerequisite that CSAP is used everywhere. Conversely, a vendor can use CSAP even if the production does not.



9 Wrap-up

This architecture is, like any architecture, a framework for building implementations. It is defined using two groupings. The first group is the set of core security components that secure production workflows. The second group is the set of supporting security components that are used by the core components. These components are available from the hyper-scale cloud providers and security-as-a-service vendors.

Our descriptions of the supporting security components are not intended to imply how they should be implemented or divided up. The interfaces between the core and supporting security components are interfaces between the core security components and a black box that contains services that provide the requisite functionality.

The core security components connect to the workflow management system since it is the system that determines what activities should take place and therefore what should be authorized. The security architecture does not, and should not, define how the production management system operates. The only requirement is that production management use the defined interfaces.

With that in mind, we can redraw the high-level architecture diagram presented earlier, Figure 4, in this way:




Figure 22 High-level architecture re-expressed

Even though there are complex interactions happening to secure a production, it is important to note that most of the services are never exposed to creatives involved in a production workflow. If the workflow, tools, and systems are designed to be secure, the users should rarely, if ever, interact directly with the components of the security system.

One note about Figure 22: the word "interface" is used in a broad sense and does not necessarily mean an API.



9.1 Next Steps

This implementation of CSAP is underway. We expect the architecture to evolve as the industry works together to facilitate implementations.

9.1.1 Interfaces

The security of the production ecosystem is best served if the security architecture can be implemented to secure production activity regardless of the cloud service used, whether a hyper-scale provider or a private cloud, and regardless of whether more than one cloud is used. Implementation using common interfaces serves that goal and also provides interoperability, which makes it easier to reconfigure security systems using different components. Many of the interfaces between components can use existing APIs. But the architecture does include components that will require the development of new interfaces.

An important next step on the road to implementation will be determining how to leverage existing standardized or commonly used interfaces for communication between components. Where new interfaces important to production security are required and not already under development, our industry may need to work together to develop those new interfaces.

Possible areas for interface development include:

- 1. Interfaces between the core security components and the supporting security components. Part of this work could include further defining the functions performed by the supporting security components.
- 2. Interfaces between the core security components and production management. It should be anticipated that more than one set of interfaces may be needed to accommodate approaches to production management that are significantly different.
- 3. Interfaces between the policy service and the policy enforcement points. Part of this work could be defining the functions performed by each type of PEP (e.g., a PEP controlling access to assets, a PEP controlling the use of an application, etc.)
- 4. Interfaces between the core components, including development of functional specifications for the core components.

Depending on the level of interoperability required between specific components, interface development could range from best practices and conventions to fully specified APIs.

9.1.2 Policy Description

This architecture is built around authorization rules which propagate to the PEPs, the endpoints of the system. This is where the architecture is potentially most complex.

Taking advantage of the full capability of the architecture requires canonical descriptions of authorization policy requests, authorization rules and global security policies. One next step is the definition of policy description.